

CapturaTalk Installation Guide

Introduction

There are two common methods by which you can install CapturaTalk onto your Windows Mobile device.

- 1) Download and extract the installation file on your PC. Copy the extracted installation file to your device via a USB connection etc.
- 2) If you device has internet access and sufficient available storage space you could download and extract the installation files on the device and install CapturaTalk.

Method 1


Requirements

- A PC with connection to the internet
- Connection between you Windows Mobile Device and your PC.
 - If running MS Windows Vista you will require [Microsoft Mobile Device Center 6.1](#)
 - If running MS Windows XP or earlier you will require [Microsoft Active Sync 4.5](#)


Walkthrough

On your PC:

- 1) Download CTinstall.zip to your computer.
- 2) Right Click on CTinstall.zip and choose "Extract all" from the context menu. Follow the onscreen instructions.



- 3) Once extracted connect your Windows Mobile device to your PC (Consult your devices manual for details). Once connected copy CTInstall.cab to your Windows Mobile Device (your device should appear in “My Computer” under XP or “Computer” under Vista). You can copy the install file to a location of your choice though we recommend your device’s “My Documents” folder.




On your Windows Mobile Device:


- 4) Tap “Start”
- 5) Tap “Programs”




- 6) Open “File Explorer”




- 7) Navigate to the location where you pasted CTInstall.cab (My Documents in step 3)



- 8) Open CTInstall.cab to begin the installation



- 9) The installation will take a moment to begin. You will then be prompted to “Choose a location to install ‘Raspberry CapturaTalk’”. Select a location that has at least 35MB free and tap “Install”. (Space required and space free is displayed for the selected installation location)



- 10) The install will proceed. Once complete tap “ok”

CapturaTalk is now ready to use and can be accessed from “Programs” or via the “Always Active CapturaTalk Menu” in the notification area.



We recommend that, once installation is complete, you remove CTInstall.cab to save storage space.

Method 2


Requirements

- An active internet connection on your Windows Mobile Device (over WiFi or Mobile Network etc)

Walkthrough

On your Windows Mobile Device:


- 1) Download CTInstall.zip to your device (My Documents folder recommended)
- 2) Navigate to CTInstall.zip (My Documents, step 1)




- 3) Open CTInstall.zip
- 4) Expand the zip and select CTInstall.CAB.



- 5) Tap "Menu" and choose extract. Extract the file to a location of your choice (My Documents)




6) Once extracted navigate to CTInstal.CAB



- 7) Open CTInstall.cab to begin the installation



- 8) The installation will take a moment to begin. You will then be prompted to “Choose a location to install ‘Raspberry CapturaTalk’”. Select a location that has at least 35MB free and tap “Install”. (Space required and space free is displayed for the selected installation location)



9) The install will proceed. Once complete tap "ok"

CapturaTalk is now ready to use and can be accessed from "Programs" or via the "Always Active CapturaTalk Menu" in the notification area.



We recommend that, once installation is complete, you remove CTInstall.cab and CTInstall.zip to save storage space.